

TABLES AND COLUMNS DEPRECATED		.NET version
MA_BLDG_AREA	Table replaced by MA_BLDG_AREA_YEAR	
MA_BLDG_AREA_YEAR		
LAST_MODIF_UID		
LAST_MODIF_DATE		
MA_BLDG_DRAWING		
APEX_SKETCH_STRING	Apex Base 64 encoded drawing	
LAST_MODIF_UID		
LAST_MODIF_DATE		
MA_BUILDINGS		
MAF_OVERRIDE_PERCENT	Contains the overriden global adjustment percentage	6.1.1508
TOTAL_VALUE_OVERRIDE	Contains the overriden total value	6.1.1508
TEMPLATE_BSE_CD	Column dropped. Not longer needed by GNA	6.1.1508
TEMPLATE_BSE_VA	Column dropped. Not longer needed by GNA	6.1.1508
MA_INCOME		
RECORD_TYPE	e' or 'a'	
LAND_VALUE_OVERRIDE	Contains the overriden land value	6.1.1508
BLDG_VALUE_OVERRIDE	Contains the overriden bldg value	6.1.1508
MISC_VALUE_OVERRIDE	Contains the overriden misc value	6.1.1508
EXISTED	DIR_RATE_OVERRIDE	0 or -1 if the dir rate is overriden
	DIR_RATE_AMOUNT_OVERRIDE	Contains the overriden dir rate when DIR_RATE_OVERRIDE = -1
EXISTED	GRM_RATE_OVERRIDE	0 or -1 if the grm rate is overriden
	GRM_RATE_AMOUNT_OVERRIDE	Contains the overriden grm rate when GRM_RATE_OVERRIDE = -1
	GROSS_RENT_PCT_OVERRIDE	Contains the overriden gross rent pct value when GROSS_OVERRIDE = -1
	RENT_UNITS_OVERRIDE	Contains the overriden rent units value when GROSS_OVERRIDE = -1
	VACANCY_PCT_OVERRIDE	Contains the overriden vacancy percent when VACANCY_PCT_OV = -1
	GROSS_EFFECTIVE_OVERRIDE	Contains the overriden gross effective value when OV_GROSS_EFF = -1
	NET_VALUE_OVERRIDE	Contains the overriden net value when OVERRIDE_NET = -1
	NET_DIR_OVERRIDE	Contains the overriden DIR value when OVERRIDE_DIR = -1
	NET_GRM_OVERRIDE	Contains the overriden DIR value when OVERRIDE_GRM = -1
	GROSS_RENT_VALUE_OVERRIDE	Contains the overriden gross rent value when GROSS_RV_OVERRIDE = -1
MA_LAND		
ADJ_TOTAL_AG	Contains the land adjustment amount for the Land AG value	
TEMPLATE_ADJ_CD	Column dropped. Not longer needed by GNA	6.1.1508
TEMPLATE_ADJ_AM	Column dropped. Not longer needed by GNA	6.1.1508
TEMPLATE_ADJ_OV	Column dropped. Not longer needed by GNA	6.1.1508
TOTAL_VALUE_OVERRIDE	Contains the overriden land value	6.1.1508
TOTAL_VALUE_AG_OVERRIDE	Contains the overriden land AG value	6.1.1508
AG_OVERRIDE	0 or -1 if the land AG value is overriden	6.1.1508

MA_LD_INFO	Table merged into MA_LAND	
MA_LOOKUP_GROUP	New table - Mass appraisal look up group for parameters	6.1.1501
LOOKUP_GROUP_ID	look up group id	
YEAR_ID		
TABLE_NAME	Table Name from MA_TABLES	
LOOKUP_GROUP_TYPE	Look up group type from ma_tables	
JURISDICTION	Jurisdiction Code from pc_parcel	
NBHD	from pc_area	
INC_NBHD	from pc_area	
PROPERTY_TYPE	from ma_parm_buse, luse, muse	
CAMA_CODE	Parameter code being indexed	
LOOKUP_GROUP	Value to be used in all MA_PARM_XXXX tables to replace simulation code	
MA_MASTER		
MRA_LAND_AMT	New column to sum all land records having INC_MRA = -1	6.1.1508
MRA_LAND_OV	New column to overide the land value to be added to MRA	6.1.1508
MRA_BLDG_AMT	New column to sum all land records having INC_MRA = -1	6.1.1508
MRA_BLDG_OV	New column to overide the land value to be added to MRA	6.1.1508
MRA_MISC_AMT	New column to sum all land records having INC_MRA = -1	6.1.1508
MRA_MISC_OV	New column to overide the land value to be added to MRA	6.1.1508
COMPUTE_LAND	Column dropped	6.1.1508
COMPUTE_PA_LAND	Column dropped	6.1.1508
COMPUTE_INC	Column dropped	6.1.1508
COMPUTE_MISC	Column dropped	6.1.1508
COMPUTE_BLDG	Column dropped	6.1.1508
COMPUTE_PP	Column dropped	6.1.1508
COMPUTE_MRA	Column dropped	6.1.1508
MA_MRA		
LAND_VALUE_OVERRIDE	Contains the overriden land value	6.1.1508
BLDG_VALUE_OVERRIDE	Contains the overriden bldg value	6.1.1508
MISC_VALUE_OVERRIDE	Contains the overriden misc value	6.1.1508
TOTAL_VALUE_OVERRIDE	Contains the overriden total value	6.1.1508
TEMPLATE_MRA_CD	Column dropped	6.1.1508
TEMPLATE_MRA_AM	Column dropped	6.1.1508
TEMPLATE_MRA_OV	Column dropped	6.1.1508
MA_PARM_XXX	All MA_PARM Tables	6.1.1501
NBHD_CODE	Column dropped. Now defined in MA_LOOKUP_GROUP	
SIMULATION	Column dropped. Now defined in MA_LOOKUP_GROUP	
MA_PARM_BOECKH	Table dropped	6.1.1508

MA_PARM_DEPR		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
MA_PARM_DRAWING		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
DRAW_STYLE	Column dropped	6.1.1501
DRAW_LWIDTH	Column dropped	6.1.1501
PATT_CODE	Column dropped	6.1.1501
PATT_BCOL	Column dropped	6.1.1501
PATT_FCOL	Column dropped	6.1.1501
PATT_SFBC	Column dropped	6.1.1501
MA_PARM_INCMODEL		
CLUSTER_CODE	Column dropped	6.1.1508
MA_PARM_L_ASSMT		
PROPERTY_TYPE	Column dropped. Now defined in MA_LOOKUP_GROUP	6.1.1508
MA_PARM_LANDADJT		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
MA_PARM_LANDRATE		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
RATE_FORMULA		6.1.1501
RATE_LOGEXP		6.1.1501
MA_PARM_LANDSCHD		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
MA_PARM_LANDUSE		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501

LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
MA_PARM_MAROUND		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
MA_PARM_MRA_PUSES		
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
MA_PARM_MRAMODEL		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
MA_PARM_NBHD		INCOME_FACTOR, INCOME_FORMULA, INCOME_LOGEXP
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
MA_PARM_SITE		
SIMULATION	Column dropped (replaced by LOOKUP_GROUP)	6.1.1501
LOOKUP_GROUP	Lookup Group Id as per MA_LOOKUP_GROUP table	6.1.1501
EXCLUDE_VALUE	-1 if this record is not being used	6.1.1501
USE_DEFAULT_VALUE	-1 if the default value for the lookup group should be used	6.1.1501
MA_SITE		
PP_VALUE	New column to track Personal Property Value	6.1.1502 Keep original value when using override
PP_LK_VALUE	New column to track Personal Property Value for linked properties	6.1.1502
LAND_OVERRIDE	New column to override Land Value (0 or -1)	6.1.1502
LAND_AG_OVERRIDE	New column to override Land AG Value (0 or -1)	6.1.1502
BLDG_OVERRIDE	New column to override Building Value (0 or -1)	6.1.1502
MISC_OVERRIDE	New column to override Misc. Structures Value (0 or -1)	6.1.1502
INC_GRM_OVERRIDE	New column to override Income GRM Value (0 or -1)	6.1.1502
INC_DIR_OVERRIDE	New column to override Income DIR Value (0 or -1)	6.1.1502
MRA_OVERRIDE	New column to override MRA Value (0 or -1)	6.1.1502
PP_OVERRIDE	New column to override Personal Property Value (0 or -1)	6.1.1502
CAMA_VALUE	New column to store to CAMA value	6.1.1508
INCOME_LAND_AMT	New column to sum all land records having INC_INCOME = -1	6.1.1508
MRA_LAND_AMT	New column to sum all land records having INC_MRA = -1	6.1.1508
INCOME_LAND_OV	New column to override the land value to be added to income	6.1.1508

MRA_LAND_OV	New column to overide the land value to be added to MRA	6.1.1508
INCOME_BLDG_AMT	New column to sum all land records having INC_INCOME = -1	6.1.1508
MRA_BLDG_AMT	New column to sum all land records having INC_MRA = -1	6.1.1508
INCOME_BLDG_OV	New column to overide the land value to be added to income	6.1.1508
MRA_BLDG_OV	New column to overide the land value to be added to MRA	6.1.1508
INCOME_MISC_AMT	New column to sum all land records having INC_INCOME = -1	6.1.1508
MRA_MISC_AMT	New column to sum all land records having INC_MRA = -1	6.1.1508
INCOME_MISC_OV	New column to overide the land value to be added to income	6.1.1508
MRA_MISC_OV	New column to overide the land value to be added to MRA	6.1.1508
LAND_VALUE_OVERRIDE	New column that contains the overriden value for land	6.1.1508
LAND_AG_VALUE_OVERRIDE	New column that contains the overriden value for land AG	6.1.1508
BLDG_VALUE_OVERRIDE	New column that contains the overriden value for bldg	6.1.1508
MISC_VALUE_OVERRIDE	New column that contains the overriden value for misc	6.1.1508
INCOME_GRM_VALUE_OVERRIDE	New column that contains the overriden value for income GRM	6.1.1508
INCOME_DIR_VALUE_OVERRIDE	New column that contains the overriden value for income DIR	6.1.1508
MRA_VALUE_OVERRIDE	New column that contains the overriden value for MRA	6.1.1508
PP_VALUE_OVERRIDE	New column that contains the overriden value for Personal Property	6.1.1508
TEMPLATE_CD	Column dropped	6.1.1508
TEMPLATE_VA	Column dropped	6.1.1508
MA_TABLES		LOOKUP_GROUP_TYPE
USE_NBHD	Column dropped (replaced by MA_LOOKUP_GROUP.NBHD)	6.1.1501
JURISDICTION	Column dropped (replaced by MA_LOOKUP_GROUP.JURISDICTION)	6.1.1501
MATRIX1_TABLE_NAME	Table name when a Matrix element 1 is being used	6.1.1501
MATRIX2_TABLE_NAME	Table name when a Matrix element 2 is being used	6.1.1501
MATRIX3_TABLE_NAME	Table name when a Matrix element 3 is being used	6.1.1501
MATRIX4_TABLE_NAME	Table name when a Matrix element 4 is being used	6.1.1501
PC_PARCEL_PICTURE	New Table - Contains a building picture extracted from Multimedia	6.1.1501
P_ID		
BLDG_PICTURE	Building Picture (Embedded Binary format)	
LAST_MODIF_UID		
LAST_MODIF_DATE		